



## Generic Emacs Bindings

|             |  |
|-------------|--|
| M-          | Meta modifier (usually Alt or Esc key) |
| C-          | Control modifier                       |
| S-          | Shift modifier                         |
| C-x C-c     | exit Emacs                             |
| C-g         | abort current command                  |
| M-x command | call function command                  |
| C-h b       | describe all key bindings              |

## File Manipulation

|           |                              |
|-----------|------------------------------|
| C-x C-f   | open a new file              |
| C-x C-s   | save current file            |
| C-x b     | switch between opened files  |
| C-x b TAB | list opened files and switch |
| C-x k     | close current file           |

## Compiling

|         |                              |
|---------|------------------------------|
| C-c C-c | compile                      |
| C-x '   | goto next error (also C-g p) |
| C-g p   | goto previous error          |

## Windows

|         |                                       |
|---------|---------------------------------------|
| C-x 5 f | open file in new frame                |
| C-x 5 b | switch to opened file in new frame    |
| C-x 5 0 | close current frame                   |
| C-x 1   | unsplit current window (if splitted)  |
| C-x 2   | split window horizontally             |
| C-x 3   | split window vertically               |
| C-x o   | switch focus between splitted windows |

## Navigation

|               |                                   |
|---------------|-----------------------------------|
| C-a           | go to beginning of line           |
| C-e           | go to end of line                 |
| C-Home        | go to beginning of file           |
| C-End         | go to end of file                 |
| C-Left        | go backward one word              |
| C-Right       | go forward one word               |
| C-Up          | go backward one paragraph         |
| C-Down        | go forward one paragraph          |
| M-g g         | goto line number                  |
| M-x goto-char | go to position                    |
| C-l           | center window on current position |

## Editing

|              |                          |
|--------------|--------------------------|
| C-_          | undo last operation      |
| C-t          | permute two letters      |
| C-k          | cut end of line          |
| M-d          | cut end of word          |
| C-backspace  | cut beginning of word    |
| M-u          | end of word to uppercase |
| M-l          | end of word to lowercase |
| C-d          | delete current character |
| C-num letter | print num times letter   |

## Search and Replace

|                    |                               |
|--------------------|-------------------------------|
| C-s                | incremental forward search    |
| C-r                | incremental backward search   |
| M-x replace-string | replace string                |
| M-x replace-regexp | replace regexp                |
| M-%                | query before replacing string |
| C-M-%              | query before replacing regexp |

## Selection (copy and paste)

|         |  |
|---------|--|
| C-Space | start selecting text                     |
| M-w     | copy selection                           |
| C-w     | cut selection                            |
| C-y     | paste selection                          |
| M-y     | circulate between selections (after C-y) |

## Tuareg Key Bindings

### Using type information

You must have compiled your code with the `-annot` option.

|                |                       |
|----------------|-----------------------|
| C-mouse-2      | caml-types-explore    |
| C-c C-t        | caml-types-show-type  |
| <i>unbound</i> | caml-types-show-ident |

### Edting

|          |  |
|----------|--|
| C-c C-q  | tuareg-indent-phrase                       |
| C-c home | tuareg-move-inside-module-or-class-opening |
| C-M-h    | tuareg-mark-phrase                         |
| C-M-\    | indent-region                              |
| C-x n d  | tuareg-narrow-to-phrase                    |

### Interaction with the Toplevel

|         |                                      |
|---------|--------------------------------------|
| C-c C-s | tuareg-run-caml                      |
| C-x C-e | tuareg-eval-phrase                   |
| C-c C-e | tuareg-eval-phrase                   |
| C-M-x   | tuareg-eval-phrase                   |
| C-c '   | tuareg-interactive-next-error-source |
| C-c C-b | tuareg-eval-buffer                   |
| C-c C-r | tuareg-eval-region                   |
| C-c C-k | tuareg-kill-caml                     |

### Navigation

|            |  |
|------------|--|
| C-c C-a    | tuareg-find-alternate-file (switch between .ml/.mli files) |
| C-c C-down | tuareg-next-phrase   |
| C-M-down   | tuareg-next-phrase   |
| C-c C-n    | tuareg-next-phrase   |
| C-M-n      | tuareg-next-phrase   |
| C-M-p      | tuareg-previous-phrase                                     |
| C-c C-up   | tuareg-previous-phrase                                     |
| C-c C-p    | tuareg-previous-phrase                                     |
| C-M-up     | tuareg-previous-phrase                                     |

## Help and Completion

|         |                    |
|---------|--------------------|
| C-c h   | caml-help          |
| C-c TAB | tuareg-complete    |
| C-c [   | ocaml-open-module  |
| C-c ]   | ocaml-close-module |
| C-c i   | ocaml-add-path     |

## Inserting Constructions

|         |                                |
|---------|--------------------------------|
| C-c . b | tuareg-insert-begin-form       |
| C-c . c | tuareg-insert-class-form       |
| C-c . f | tuareg-insert-for-form         |
| C-c . i | tuareg-insert-if-form          |
| C-c . l | tuareg-insert-let-form         |
| C-c . m | tuareg-insert-match-form       |
| C-c . t | tuareg-insert-try-form         |
| C-c . w | tuareg-insert-while-form       |
| C-x C-x | Switch between mark and cursor |

## Emacs Configuration

### Sample ~/.emacs file

```
(setq auto-mode-alist
  (cons '("\\.ml\\w?" . tuareg-mode)
    auto-mode-alist))
(autoload 'tuareg-mode "tuareg"
  "Major mode for editing Caml code" t)
(autoload 'camldebug "camldebug"
  "Run the Caml debugger" t)
(if (and (boundp 'window-system) window-system)
  (when (string-match "XEmacs" emacs-version)
    (if (not (and (boundp 'mule-x-win-initted)
      mule-x-win-initted))
      (require 'sym-lock))
    (require 'font-lock)))
  (require 'font-lock)))
(add-hook 'tuareg-mode-hook '(lambda ()
  (define-key tuareg-mode-map "\M-q"
    'tuareg-indent-phrase)
  (define-key tuareg-mode-map "\C-c \C-i"
    'caml-types-show-ident)
  (define-key tuareg-mode-map [f4] 'goto-line)
  (define-key tuareg-mode-map [f5] 'compile)
  (define-key tuareg-mode-map [f6] 'recompile)
  (define-key tuareg-mode-map [f7] 'next-error)
  (auto-fill-mode 1)
  (setq tuareg-sym-lock-keywords nil) ))
(setq column-number-mode t)
(setq mouse-wheel-follow-mouse t)
(setq standard-indent 2)
(transient-mark-mode 1)
(setq visible-bell t)
(setq show-paren-face 'modeline)
(setq global-font-lock-mode t)
(setq global-auto-revert-mode t)
```